


Benjamin Moore & Co. Moore's COLOR_x® System Release Notes & Installation Guide Version 6.28.2000



COLOR_x version 6.28.2000 contains updated Benjamin Moore prescriptions. For a complete list of updated prescriptions, see page 2.

New Product in Canada

Super Hide Zero VOC Interior Finishes K355, K356, K357, K358

Colonial Williamsburg Colors

Now available in Arborcoat (640, K640) and Natura products 512, 513, 514, K513, K514, K516)

New Competitive Color Collections

The following color collections have been added to this release of COLOR_x.

- 1- Valspar
- 2- Behr Marquee

Help

While in the COLOR_x application, you can view the Operator's Manual and the Quick Start Guide by clicking on Help, then choose COLOR_x Help for the manual or COLOR_x Quick Start.

Competitive Color Prescriptions

We have amassed an extensive collection of colors from our competitor's color merchandise. This information is available in our Color Search option in COLOR_x. To see if a color exists, simply follow the same procedure you would for a Benjamin Moore color. Enter a color number or name, along with a product, and either select an individual company or check the "Search All" box above the Select Company drop down list.

Unlike a Benjamin Moore color which displays a prescription created and tested by our Color Prescribing Lab, we store just the measurement of the competitive color. That measurement is run in our color matching application to generate a color prescription the same as if you measured a custom color with a spectrophotometer and calculated a match.

Therefore, when a customer requests a match to a competitive color, a retailer should follow this procedure. First, look up the color in COLOR_x and determine if we have it in our system. If it is, a prescription will be calculated and displayed. Click on the button "Closest BM Color", this will list the five closest Benjamin Moore colors. Suggest to the customer that they look at our closest colors and see if that meets their color requirements. This has two benefits, if the color is acceptable, then you have a tested Benjamin Moore prescription to make the color and you have changed a competitive color specification to a Benjamin Moore color specification.

Second, if you or the customer has a sample of the competitive color merchandise then match the color merchandise just as you would match a custom color. Since the customer will be judging the color to the merchandise sample that should be your target. Depending on the age and condition of the merchandise, it may not represent what we have stored in COLOR_x.

Finally, if the customer does not like our closest color and no sample of the color is available then use the calculated match in COLOR_x.

If you have any questions, please contact your Color Technology Rep. or call 800-809-9213.

Prescription Changes since COLOR_x Version 6.28.1000 (United States)

The prescriptions for product N1221X have been modified for improved matches.

The following colors had their prescriptions changed in several products: 2161-10, PM-1. Please refer to the revision date when calling up prescriptions for these colors. A revision date after 4/22/2014 indicates a change in the prescription since COLOR_x version 6.28.1000.

The following prescription has been modified for product 147: 2165-60

The following prescription has been modified for product 148: 2165-60

The following prescription has been modified for product 513: 2108-50

The following prescriptions have been modified for product 524: 2139-50, AF-115

The following prescription has been modified for product 528: 199

The following prescription has been modified for product 532: 2130-60

The following prescriptions have been modified for product 550: 1048, 2134-10, HC-37

The following prescriptions have been modified for product 792: 1650, 2144-70, 2165-60, HC-85, HC-155, HC-159, OC-118

The following prescription has been modified for product 793: 2165-60

The following prescription has been modified for product 824: 292

The following prescription has been modified for product N310: 177

The following prescription has been modified for product N314: 2139-50

The following prescription has been modified for product N322: 177

The following prescriptions have been modified for product N401: 347, 368

The following prescription has been modified for product N403: 2015-10

The following prescriptions have been modified for product N538: 200, HC-12

The following prescription has been modified for product N794: 2165-60

The following prescription has been modified for product W096: 2015-10

The following prescriptions have been modified for product W103: 331, 345, 347, 368, 374, 386, 388, 393, 423, 477, 881, 1472, 1499, 1513, 1534, 1562, 1564, 1583, 1584, 1586, 1591, 1592, 1632, AC-25, OC-29, OC-138

The following prescription has been modified for product W625: 292

The following prescriptions have been modified for product W627: 2139-30, 2139-50

Prescription Changes since COLORx Version 6.28.1000 (Canada)

The prescriptions for product F1221X have been modified for improved color matches.

The following colors had their prescriptions changed in several products: 2161-10, PM-1. Please refer to the revision date when calling up prescriptions for these colors. A revision date after 4/22/2014 indicates a change in the prescription since COLORx version 6.28.1000.

The following prescription has been modified for product F794: 2165-60

The following prescription has been modified for product K401: OR-278

The following prescription has been modified for product K513: 2108-50

The following prescriptions have been modified for product K524: 2139-50, AF-115

The following prescription has been modified for product K528: CC-180

The following prescription has been modified for product K532: 2130-60

The following prescriptions have been modified for product K550: 2134-10, HC-37

The following prescriptions have been modified for product K552: CC-540, OR-25

The following prescriptions have been modified for product K538: HC-12

The following prescriptions have been modified for product K627: 2139-30, 2139-50

The following prescriptions have been modified for product K792: 2144-70, 2165-60, HC-85, HC-155, HC-159, OC-118

The following prescription has been modified for product K793: 2165-60

Moore's COLOR_x® System Installation Guide

The Benjamin Moore COLOR_x Prescription Book and Color Matching System programs are incorporated into a single software package. It is available on the Benjamin Moore Retailer Portal, Mybenjaminmoore.com and runs under the Windows® XP, Windows® Vista, and Windows® 7 operating systems.

Minimum System Requirements

- Intel Pentium® processor 500 MHz or higher.
- 1 GB of RAM
- 750 MB of free hard disk space.
- CD or DVD Drive
- Video card capable of supporting 16M colors
- Printer
- Serial or USB port for spectrophotometer
- Windows® XP, Windows® Vista or Windows® 7

Installation

If you are downloading COLOR_x from the Benjamin Moore Retailer Portal, mybenjaminmoore.com, read the "COLOR_x Download Instructions." This will instruct you how to download and install COLOR_x on your computer.

To install COLOR_x from a CD, you must have the Windows desktop displayed. If there are any other applications running, they should be closed before attempting to install the program. If your system has any automatic virus detection software enabled, it should be disabled before installing.

Insert the CD labeled "COLOR_x System" into the CD drive.

The installation procedure will automatically start and bring you to the **Welcome Screen**.

If the installation does not automatically start, click on the "Start" button, usually found at the lower left corner of the screen. The primary menu will pop up. Click on "Run..." and the "Run" dialog box will display. Type "**D:\SETUP**" (where "**D:**" is the designated drive letter for the CD) on the "Open" line and click on "OK".

The Setup Wizard will guide you through the installation.

License Agreement

As you start the installation, the License Agreement screen appears. Be sure to read this license agreement. If you disagree with the terms of the agreement, then click on the Cancel button to exit the installation. If you agree with the terms, then check the appropriate box to continue the installation. The installation will prompt you to select the software region, United States or Canada. The default is United States.

After the successful installation of the software you may be prompted to reboot your system.

Note: If you have a previous version of COLOR_x® 6, this installation will not write over any stored samples or stored customers. They can be still be accessed.