

Benjamin Moore & Co. Moore's COLOR_x® System Release Notes & Installation Guide Version 6.38.2000



This new COLOR_x release contains the following changes to COLOR_x

Colonial Williamsburg Colors

Prescriptions for the Colonial Williamsburg colors are now available for the interior ben® products in the U.S. and Canada.

National Accounts Colors Added

Colors for: CORA Physical Therapy, Sharkey's Cuts for Kids, Key Structures, Goodwin Knight, Carter Hill Homes, Christmas Tree Shops & That!, Tend, Tishman Speyer Real Estate, PM Pediatrics, and Coffee Beanery.

Benjamin Moore Prescriptions

For the complete list of updated prescriptions, see page 3.

New Competitive Color Collection

The following color collection has been added to this release of COLOR_x:
Kelly-Moore's Historic Lifestyles of the West (106) colors

New Dymo 550/550 Turbo LabelWriter Printers

Dymo has recently introduced the LabelWriter 550 and LabelWriter 550 Turbo label printers. Be advised that these printers only work with genuine Dymo labels. They will not work with labels from third party label vendors.

Weekend Technical Support

Technical support is limited on the weekends. Please refrain from doing updates during this time, and limit calls to situations where you are not able to tint paint.

COLOR_x Help

While in the COLOR_x application, you can view the Operator's Manual and the Quick Start Guide by clicking on Help, then choose COLOR_x Help for the manual or COLOR_x Quick Start.

Best Practices for Custom Color Matching and Competitive Company Colors

Always save and store custom matched color formulas and competitive company formulas made for your customers in the Customer File database in COLOR_x. This will assure that you have the exact formula that the customer previously purchased.

We routinely update our calibration database files to improve our color matching capabilities, which may alter the original formula.

Following this procedure will allow the customer to purchase the same formula in the event that they return to purchase more of this color for touch up.

Competitive Color Prescriptions

We have amassed an extensive collection of colors from competitor's color merchandise. This information is available in our Color Search option in COLOR_x. To see if a color exists, simply follow the same procedure you would for a Benjamin Moore color. Enter a color number or name, along with a product, and either select an individual company or check the "Search All" box above the "Select Company" drop down list. (See the Operator's Manual for more details.)

Unlike a Benjamin Moore color that displays a prescription created and approved by our Color Prescribing Lab, we store the measurement of the competitive color. The measurement is calculated in our color matching application to generate a color prescription the same as if you measured a custom color with a spectrophotometer.

When a customer requests a match to a competitive color, you should follow this procedure. First, look up the color in COLOR_x and determine if we have it in our system. If it is, a prescription will be calculated and displayed. Click on the button "Closest BM Color", this will list the five closest Benjamin Moore colors. Suggest to the customer that they look at our closest colors and see if that meets their color requirements. This has two benefits. If the color is acceptable, then you have a tested Benjamin Moore prescription to make the color and you have changed a competitive color specification to a Benjamin Moore color specification.

Second, if you or the customer has a sample of the competitive color merchandise then match the color merchandise just as you would match a custom color. Since the customer will be judging the color to the merchandise sample that should be your target. Depending on the age and condition of the merchandise, it may not represent what we have stored in COLOR_x.

Finally, if the customer does not like our closest color and no sample of the color is available then use the calculated match in COLOR_x.

If you have any questions, please contact technical support at 800-809-9213.

Prescription Changes since COLORx Version 6.38.1000 (United States)

The BM Core Color prescriptions for the Aura Exterior products N634, N631, N632, and N629 have been changed.

Color prescriptions have been updated for the 127 and 200 color samples.

Color prescriptions have been added for the Colonial Williamsburg color collection for all ben interior products.

The color prescriptions for color 2125-40 have been modified for the following products: 541, 447, 610, 763, HP25, HP28, HP29.

The color prescriptions for colors 967, CC-40 and OC-130 have been modified for the following product: N448.

The color prescriptions for colors 003, 031, 096, 137, 2102-70, 347, 375, 389, 1285, 1297, and 1319 have been modified for the following product: T538.

The color prescriptions for colors 826, 1547, 2138-20, AF-290, CC-870 have been modified for the following product: N538 and T538.

Prescription Changes since COLORx Version 6.38.1000 (Canada)

The BM Core Color prescriptions for the Aura Exterior products F634, F631, F632, and F629 have been changed.

Color prescriptions have been updated for the K127 and K200 color samples.

Color prescriptions have been added for the Colonial Williamsburg color collection for all ben interior products.

The color prescriptions for color 2125-40 have been modified for the following products: K541, K447, K610, K763.

The color prescriptions for colors 967, CC-40 and OC-130 have been modified for the following product: K448.

The color prescriptions for colors 003, 031, 096, 137, 347, 375, 389, 826, 1285, 1297, 1319, 1547, 2138-20, AF-290, and CC-870 have been modified for the following product: F538.

Moore's COLOR_x® System Installation Guide

The Benjamin Moore COLOR_x Prescription Book and Color Matching System programs are incorporated into a single software package. It is available on the Benjamin Moore Retailer Gateway, retailer.benjaminmoore.com and runs on the Windows® XP service pack 3, Windows® 7, Windows® 8, and Windows® 10 operating systems.

COLOR_x Minimum System Requirements

- Intel Pentium® processor 1 GHz or higher.
- 2 GB of RAM
- 4 GB of free hard disk space.
- Video card capable of supporting 16M colors
- Printer
- Serial or USB port for spectrophotometer & barcode reader
- Windows® XP service pack 3, Windows® Vista, Windows® 7, Windows® 8 or Windows® 10

X-Rite MetaVue and i1 Paint Spectrophotometer Minimum System Requirements

- Windows 7 SP1 (32 or 64 bit)
- Windows 8/8.1 (32 or 64 bit)
- Windows 10 (32 or 64 bit)

Windows® XP and Vista are not supported for these spectrophotometers

Installation

If you are downloading COLOR_x from the Benjamin Moore Retailer Gateway, retailer.benjaminmoore.com, the file will automatically download to the default location for your web browser after clicking on the DOWNLOAD button. After the download has completed, close running versions of COLOR_x, double-click the downloaded file, and follow the prompts to install.

If you don't have internet access on the computer running COLOR_x, you can download the COLOR_x installation file directly to a flash drive from another computer which has internet access.

To install COLOR_x from a flash drive, be sure that there are no other applications running. They should be closed before attempting to install the program. If your system has any automatic virus detection software enabled, it should be disabled before installing.

Insert the flash drive into a USB port. Open Windows Explorer and click on the flash drive letter. Now click on the ColoRx6xxxxxx.exe file.

The installation procedure will automatically start and bring you to the **Welcome Screen**. The Setup Wizard will guide you through the installation.

License Agreement

As you start the installation, the License Agreement screen appears. Be sure to read this license agreement. If you disagree with the terms of the agreement, then click on the Cancel button to exit the installation. If you agree with the terms, then check the appropriate box to continue the installation. The installation will prompt you to select the software region, United States or Canada. The default is United States.

Note: If you have a previous version of COLOR_x 6, this installation will not write over any stored samples or stored customers. They can still be accessed.