

Benjamin Moore & Co. Moore's COLOR_x® System Release Notes & Installation Guide Version 6.40.1000



This new COLOR_x release contains the following changes to COLOR_x

COLOR_x 7

COLOR_x 7 is scheduled to begin rolling out in Q1 2025. In preparation, retailers are asked to assess their readiness by running the COLOR_x 7 Compatibility Testing Tool, which can be downloaded from the Retailer Gateway, on each PC running their current version of COLOR_x. It is located just below the section where the COLOR_x update is located. Once the compatibility tool has been run on all PCs running COLOR_x 6, please register your results by using the registration form found here: [COLOR_x 7 Registration Form](#). This test will identify computers that do not meet the minimum system requirements for COLOR_x 7.

New High Performance “HP” Products – Phase 2

Prescriptions and color matching ability has been added for following products in the U.S. and Canada: HP2200, HP2210, HP2220, HP3300, HP3310, HP3320, HP4100 and HP5010. In addition, products CHP2200, CHP2210, CHP2300, HP2300, HP2400, and HP5200 will be available only in the U.S.

INSL-X Sure Step

Prescriptions and color matching ability has been added for INSL-X Sure Step (NSU10) for the U.S. and Canada. This product can be tinted with Color Preview or Gennex colorants and is available in a 1B and 4B for the U.S. and only in the 1B for Canada.

Top 250 Best Selling Colors

The top 250 best-selling colors have been exact matched in Color Samples (200/K200/U200) and Regal Select Matte (N548) in the U.S.

Benjamin Moore Prescriptions

For the complete list of updated prescriptions, see page 3.

Dymo 550/550 Turbo LabelWriter Printers

Dymo has recently introduced the LabelWriter 550 and LabelWriter 550 Turbo label printers. Be advised that these printers only work with genuine Dymo labels. They will not work with labels from third party label vendors.

Weekend Technical Support

Technical support is limited on the weekends. Please refrain from doing updates during this time, and limit calls to situations where you are not able to tint paint.

COLORx Help

While in the COLORx application, you can view the Operator's Manual and the Quick Start Guide by clicking on Help, then choose COLORx Help for the manual or COLORx Quick Start.

Best Practices for Custom Color Matching and Competitive Company Colors

Always save and store custom matched color formulas and competitive company formulas made for your customers in the Customer File database in COLORx. This will assure that you have the exact formula that the customer previously purchased.

We routinely update our calibration database files to improve our color matching capabilities, which may alter the original formula.

Following this procedure will allow the customer to purchase the same formula in the event that they return to purchase more of this color for touch up.

Competitive Color Prescriptions

We have amassed an extensive collection of colors from competitor's color merchandise. This information is available in our Color Search option in COLORx. To see if a color exists, simply follow the same procedure you would for a Benjamin Moore color. Enter a color number or name, along with a product, and either select an individual company or check the "Search All" box above the "Select Company" drop down list. (See the Operator's Manual for more details.)

Unlike a Benjamin Moore color that displays a prescription created and approved by our Color Prescription Lab, we store the measurement of the competitive color. The measurement is calculated in our color matching application to generate a color prescription the same as if you measured a custom color with a spectrophotometer.

When a customer requests a match to a competitive color, you should follow this procedure. First, look up the color in COLORx and determine if we have it in our system. If it is, a prescription will be calculated and displayed. Click on the button "Closest BM Color", this will list the five closest Benjamin Moore colors. Suggest to the customer that they look at our closest colors and see if that meets their color requirements. This has two benefits. If the color is acceptable, then you have a tested Benjamin Moore prescription to make the color and you have changed a competitive color specification to a Benjamin Moore color specification.

Second, if you or the customer has a sample of the competitive color merchandise then match the color merchandise just as you would match a custom color. Since the customer will be judging the color to the merchandise sample that should be your target. Depending on the age and condition of the merchandise, it may not represent what we have stored in COLORx.

Finally, if the customer does not like our closest color and no sample of the color is available then use the calculated match in COLORx.

Prescription Changes since COLORx Version 6.40.0000 (United States)

Color prescriptions in the 200 samples line have been updated.

Many prescriptions in product N548 have been updated since January 18th of 2024.

Color prescriptions for colors HC-182 and PM-17 have been updated in the following product: N122
Color prescriptions for colors AC-40, AF-380, AF-490, CC-20, CC-70, CC-636, CSP-15, CSP-560, HC-166, OC-149, and PM-3 have been updated in the following product: N522
Color prescriptions for colors AF-555, CSP-760, CSP-535, HC-188, and PM-11 have been updated in the following product: N524
Color prescriptions for colors AC-40, CC-70, and CC-636 have been updated in the following products: N524, N547, and N549
Color prescriptions for colors AC-40, CC-70, and CC-636 have been updated in the following products: N400, N401, N403, N526, N528, N550, N551, N624, N628, W096, W105, and W627
Color prescriptions for colors CC-410, CSP-625, HC-190, PM-9, 1102, 2060-10, 2129-10, 2131-10, 2132-10, and 2136-10 have been updated in the following product: N624
Color prescription for color 1459 in product T538 has been updated.
Color prescriptions for colors CC-30, OC-15, OC-57, HC-170, HC-173, 869, and 972 have been updated in the following product: 532
Color prescription for color 203 in product N540/ T546 has been updated.
Color prescription for color HC-154 in product N550 has been updated.
Color prescription for color 2174-30 in product N485/N486 has been updated.

Prescription Changes since COLORx Version 6.40.0000 (Canada)

Color prescriptions in the K200 samples line have been updated.

Many prescriptions in product 548 have been updated since January 18th of 2024.

Color prescriptions for colors HC-182 and PM-17 have been updated in the following product: F122
Color prescriptions for colors AC-40, AF-380, AF-490, CC-20, CC-70, CC-636, CSP-15, CSP-560, HC-166, OC-149, and PM-3 have been updated in the following product: F522
Color prescriptions for colors AF-555, CSP-760, CSP-535, HC-188, and PM-11 have been updated in the following product: F524
Color prescriptions for colors AC-40, CC-70, and CC-636 have been updated in the following products: F524, F547, and F549
Color prescriptions for colors AC-40, CC-70, and CC-636 have been updated in the following products: K400, K401, K403, F526, F528, F550, F551, F624, F628, F627, Z096, and Z105
Color prescriptions for colors CC-410, CSP-625, HC-190, PM-9, 1102, 2060-10, 2129-10, 2131-10, 2132-10, and 2136-10 have been updated in the following product: F624
Color prescription for color 1459 in product F538 has been updated.
Color prescriptions for colors CC-30, OC-15, OC-57, HC-170, HC-173, 869, and 972 have been updated in the following product: K532
Color prescription for color 203 in product F546/ K540 has been updated
Color prescription for color HC-154 in product F550 has been updated
Color prescription for color 2174-30 in product F485/F486 has been updated

Moore's COLOR_x® System Installation Guide

The Benjamin Moore COLOR_x Prescription Book and Color Matching System programs are incorporated into a single software package. It is available on the Benjamin Moore Retailer Gateway, retailer.benjaminmoore.com and runs on the Windows® XP service pack 3, Windows® 7, Windows® 8, and Windows® 10 operating systems.

COLOR_x Minimum System Requirements

- Intel Pentium® processor 1 GHz or higher.
- 2 GB of RAM
- 4 GB of free hard disk space.
- Video card capable of supporting 16M colors
- Printer
- Serial or USB port for spectrophotometer & barcode reader
- Windows® XP service pack 3, Windows® Vista, Windows® 7, Windows® 8 or Windows® 10

X-Rite MetaVue and i1 Paint Spectrophotometer Minimum System Requirements

- Windows 7 SP1 (32 or 64 bit)
- Windows 8/8.1 (32 or 64 bit)
- Windows 10 (32 or 64 bit)

Windows® XP and Vista are not supported for these spectrophotometers

Installation

If you are downloading COLOR_x from the Benjamin Moore Retailer Gateway, retailer.benjaminmoore.com, the file will automatically download to the default location for your web browser after clicking on the DOWNLOAD button. After the download has completed, close running versions of COLOR_x, double-click the downloaded file, and follow the prompts to install.

If you don't have internet access on the computer running COLOR_x, you can download the COLOR_x installation file directly to a flash drive from another computer which has internet access.

To install COLOR_x from a flash drive, be sure that there are no other applications running. They should be closed before attempting to install the program. If your system has any automatic virus detection software enabled, it should be disabled before installing.

Insert the flash drive into a USB port. Open Windows Explorer and click on the flash drive letter. Now click on the ColoRx6xxxxxx.exe file.

The installation procedure will automatically start and bring you to the **Welcome Screen**. The Setup Wizard will guide you through the installation.

License Agreement

As you start the installation, the License Agreement screen appears. Be sure to read this license agreement. If you disagree with the terms of the agreement, then click on the Cancel button to exit the installation. If you agree with the terms, then check the appropriate box to continue the installation. The installation will prompt you to select the software region, United States or Canada. The default is United States.

Note: If you have a previous version of COLOR_x 6, this installation will not write over any stored samples or stored customers. They can still be accessed.